



Spaces can be set up to be linear spaces for side tie and rafting management one of 3 ways.

1. Add an asterisk (*) as the last letter of the space name.
2. Add an asterisk (*) as the first letter of the space description (i.e. *SIDE).
3. Adding a ZZ as the first two letters of the space name (i.e. ZZGST)



#	Rank Name	Time Factor	Sur \$/%	Fist Charge	Per Foot Chr	G, S, B, #, @	Net
1	MONTHLY	Monthly	0.000	0.00	11.4000	G	= 627.00
2	ANNUAL	Annual/Seas	0.000	0.00	57.0000	G	= 3,135.00
3	SEMI-ANNUAL	Semi Ann	0.000	0.00	33.5000	G	= 1,842.50
4	DAILY	Daily	0.000	0.00	1.3500	G	= 74.25
5	WEEKLY	Weekly	0.000	0.00	5.8500	G	= 321.75
6		Daily	0.000	0.00	0.0000	G	= 0.00
7		Daily	0.000	0.00	0.0000	G	= 0.00
8		Daily	0.000	0.00	0.0000	G	= 0.00
9		Monthly	0.000	0.00	0.0000	G	= 0.00

Availability List shows linear spaces and boat in with remaining footage



(STATUS L = VACANT; TEMP. OUT INCLUDED, NOT COUNTED VACANT)
Group: ALL Date View = 03.08.04 . *****

0 FOOT

RV02 | L: , W:

30 FOOT

A4 | L:30, W:15
C4 | L:30, W:10

35 FOOT

B1 DP | L:35, W:15

40 FOOT

50 FOOT


55 FOOT

ENDA* L:= 55 TOTAL BOAT LENGTH= 35 # BOATS= 1 AVAILABLE: 20
ENDB* RAFT | L:55, W:
ENDB* L:= 55 TOTAL BOAT LENGTH= 0 # BOATS= 0 AVAILABLE: 55

100 FOOT

ZZDOCK Mem WK | L:100, W:
ZZDOCK L:= 100 TOTAL BOAT LENGTH= 0 # BOATS= 0 AVAILABLE: 100

[Search] from POS or Tenant screen shows linear space with remaining footage. See double line for space ENDB* below.




Enter search criteria and press the reload button to load the data that matches your criteria. To stop the load at any point press the stop button.

Date Range
 Start Date: 12/27/2006
 End Date: _/_/____
 Show All Dates Show Vacant Only

Space	Desc	L	W	D	H	Name	Boat	Reg #
E117		100	40	20	0	VACANT		
E118		100	40	20	0	VACANT		
EAST		200				Occ ft = 0 Vac ft =200	# Boats = 0	
ENDA*		55				Occ ft = 0 Vac ft =55	# Boats = 0	
ENDB*	*RAFT	55	0	0	0	CASTLE, DEBORAH	RUNAWAY BRIDE	CA 22213
ENDB*		55				Occ ft = 35 Vac ft =20	# Boats = 1	
RV02		0	0	0	0	VACANT		
WEST		200				Occ ft = 0 Vac ft =200	# Boats = 0	
WK01		0	0	0	0	VACANT		
WK02		0	0	0	0	VACANT		
WK03		0	0	0	0	VACANT		
WK04		0	0	0	0	VACANT		

Count 218

Print OK Close



Space

ENDB* *RAFT

Search

L: 25 L: 55
 B: 9 W: 0
 D: 6 Vac=-5
 #=2

The POS screen shows number of boats and remaining feet – in this case negative!

This displays even when the space is not yet saved, so queries can be done with a new guest reservation.

Occupancy vacancy – for all or Vacant, shows number of feet:

14:52 ROCKYBOTTOMMARINA 03-08-2004

VACANCY INVENTORY SPACE ORDER

(STATUS L, Y = VACANT; TEMP. OUT INCLUDED, NOT COUNTED VACANT)
Group: ALL Date View = 03-08-04 . *****

SPACE	TENANT	REC #	BOAT	BEAM	BOAT DRAW	LNTH	* WPTH	SPACE DPTH	LNTH
A2	MANNERS, W	2	T Gone 09-01-01 to 06-02-02				* 15.	10.	30.
A4							* 15.	0.	30.
B1	DF						* 15.	10.	35.
B2	MILLER, S	4	T Gone 09-02-01 to 12-11-01				* 15.	10.	40.
C4							* 10.	0.	30.
EAST	*RAFT						* 0.	0.	200.
EAST L:= 200 TOTAL BOAT LENGTH= 0 # BOATS= 0 AVAILABLE FOOTAGE: 200									
ENDB* L:= 55 TOTAL BOAT LENGTH= 22 # BOATS= 1 AVAILABLE FOOTAGE: 33									
ENDB* *RAFT									
ENDB* L:= 55 TOTAL BOAT LENGTH= 0 # BOATS= 0 AVAILABLE FOOTAGE: 55									
RV02							* 0.	0.	0.
WEST	*RAFT						* 0.	0.	200.
WEST L:= 200 TOTAL BOAT LENGTH= 0 # BOATS= 0 AVAILABLE FOOTAGE: 200									
ZZDOCK	Mem WK						* 0.	0.	100.
ZZDOCK L:= 100 TOTAL BOAT LENGTH= 0 # BOATS= 0 AVAILABLE FOOTAGE: 100									
TOTALS:									
UNOCCUPIED FOOTAGE:		550.0	UNOCCUPIED SPACES:		7				

Pg: 1 of 1
122%

Click on Occupancy or 'total' line and add a new tenant record to this space

Browse Occupancy

Enter search criteria and press the reload button to load the data that matches your criteria. To stop the load at any point press the stop button.

Date Range
 Start Date: 12/27/2006
 End Date: / /
 Show All Dates Show Vacant Only

Space	Desc	L:	W:	D:	H:	Name	Boat	Reg #
E117		100	40	20	0	VACANT		
E118		100	40	20	0	VACANT		
EAST		200				Occ ft = 0 Vac ft =200	# Boats = 0	
ENDB*		55				Occ ft = 0 Vac ft =55	# Boats = 0	
ENDB*	*RAFT	55	0	0	0	CASTLE, DEBORAH	RUNAWAY BRIDE	CA 22213
ENDB*		55				Occ ft = 35 Vac ft =20	# Boats = 1	
RV02		0	0	0	0	VACANT		
WEST		200				Occ ft = 0 Vac ft =200	# Boats = 0	
WK01		0	0	0	0	VACANT		
WK02		0	0	0	0	VACANT		
WK03		0	0	0	0	VACANT		
ZZDOCK		0	0	0	0	VACANT		

Count 218

Print OK Close